
ModelFactory Documentation

Table of Contents

General Description	1
Environment Setup (Model Descriptions)	2
Model Customization Options	3
Model Creation	5
Model Visualization	6
Model Export	7

Copyright (c) 2017 Manish Sreenivasa

Author: Manish Sreenivasa, manish.sreenivasa@ziti.uni-heidelberg.de, Heidelberg University, Germany


Licensed under the zlib license. See LICENSE for more details.

Developments of the toolkit can be followed on: <https://github.com/manishsreenivasa/ModelFactory>

Please cite this work as: Sreenivasa M & Harant M. (under review), "ModelFactory: A Matlab/Octave based toolbox to create human body models" submission to Source Code for Biology & Medicine

General Description

The ModelFactory toolkit consists of a set of scripts in Matlab®/Octave that can be used to create models of humans and objects. By default a graphical user interface is included that works on Matlab (tested on Matlab 2017a®). A text based interface for Octave (tested on Octave 4.2.1, <https://ftp.gnu.org/gnu/octave/>) as well as Matlab®.



Environment Setup (Model Descriptions)

The environment file provides the ModelCreator script with all information needed to initialize, create and export the models. The fields present within the environment file should point to other files that describe the model setup. Comment lines start with a #. Some sample environment files are available in data/samples. Options loaded from the environment file can still be overwritten using the menu available in the GUI.

Setting up an environment: Environment files may be loaded in the GUI using the "Load Environment Setup" button located top left. In the non-GUI version, edit ModelCreator_noGUI.m to point to the right file




```
EnvironmentSetupFile = ['data/samples/  
EnvironmentSetup_3DHumanDefault.env'];
```

Human Model Options

```
humanModel_DescriptionFile %<----- Specify source for human  
model description (mandatory)  
ModelFiles_3DHumanDefault/3DHumanDefault_Description  
%
```

A sample annotated human model description file is shown below



```

humanModel_ScalingAlgorithmChoice %<----- Specify source for
    human model scaling algorithm (mandatory)
deLeva1996_segmentedTrunk % must match one of the algorithms included
    in core/scalingAlgorithms or one provided by the user

humanModel_AnthropometryFile %<----- Specify source for human
    anthropometry (mandatory)
ModelFiles_3DHumanDefault/3DHumanDefault_Anthropometry

AddMarkers %<----- Boolean to add markers to the model
    (optional, defaults to 0/false)
1          % default VICON PIG markers are used if no custom marker
    setups are defined (see below)

```

Object Model 1 Options (optional)

```

objectModel1_DescriptionFile %<----- Specify source for model
    description of object 1
ModelFiles_3DHumanExoBox/Exo_3D_Description

objectModel1_SetupChoice %<----- Specify source for model setup
    function of object 1
Exo_3D          % must match one of the algorithms included
    in customSetups/setups or one provided by the user

objectModel1_MassProperties %<----- Specify how object mass
    should be calculated
ModelFiles_3DHumanExoBox/Exo_3D_MassProperties % (either as user
    specified values, or from segment mesh volume and segment mean
    density, or in setup function)
% A sample annotated object mass properties file is shown below

```

Exo_PelvisModule_Sagittal, UseMeanDensity, 800.0, 0.0136, 0.0, 0.0, 0.0001, 0.0001

Exo_ThighBar_Sagittal, UseUserValues, 0.876, 0.03, 0.0, -0.249, 0.0136, 0.0, 0.0, 0.0, 0.0001, 0.0001

Labels and their corresponding values:

- Exoskeleton Segment Name: Exo_PelvisModule_Sagittal, Exo_ThighBar_Sagittal
- Flag: 0.876, 0.03
- Density in kg/m³ if flag = UseMeanDensity, Mass in kg if flag = UseUserValues: 800.0, 0.0
- Center of mass in meters (in segment local coordinates): 0.0136, 0.0
- Inertia matrix in kg.m² if flag = UseUserValues: 0.0001, 0.0

Object Model 2 Options (optional) Additional objects such as boxes and other user defined elements can be created using the following options.

```

objectModel2_DescriptionFile %<----- Specify source for object
    model description 2
ModelFiles_3DHumanExoBox/Box15kg_3D_Description

objectModel2_SetupChoice %<----- Specify source for object model
    setup 2,
Box15kg_3D          % must match one of the algorithms included
    in customSetups/setups or one provided by the user

```

Model Customization Options

The following optional customization options are currently implemented.

Custom segment lengths can be used to make the human model subject-specific. Note that the segment masses and inertia are also adjusted (linearly) proportional to the provided custom lengths

```
humanModel_UseCustomLengths %<----- Specify source file for
human segment lengths
ModelFiles_3DHumanExoBox/3DHuman_SegmentLengths
%
```

Custom markers can be defined to specify lab-specific arrangements. In addition to the default VICON PIG markerset, a custom "cluster" based markerset is currently available for use.

```
UseCustomMarkers
ModelFiles_3DHumanCustom/3DHumanCustom_MarkerOptotrak
%
```


Custom constraints can be used to define additional constraints, for example between the human and the objects. For now, only loop-type custom constraints are available between the human and objects

```
humanModel_UseCustomConstraints
ModelFiles_3DHumanExoBox/3DHumanExoBox_LoopConstraints
%
```

Custom points for the foot segment can be defined using the "customOffsetFoot" keyword in the corresponding dictionary term. If this keyword is present, then the values in the field "rel_functional_distance" are used (instead of rel_position_to_joint_center). The foot points are then computed as:

```
point = [rfd(1)*l_foot-heelAnkleXOffset
         rfd(2)*footWidth
         -heelAnkleZOffset];
```

where the vector rfd refers to the rel_functional_distance specified for that point. l_foot is the foot segment length, and the values of heelAnkleXOffset, footWidth and heelAnkleZOffset are specified in the subject anthropometry file.




Two type of mesh options are available, "default" and "human". Default meshes plot the human limbs using simple cylindrical and other basic shapes. Human meshes have been derived from the MakeHuman

software <http://www.makehuman.org/>, and are based on a neutral-gendered character. Note that if you use human meshes alongwith custom segment scaling you probably have to play around with the mesh dimensions and mesh centers (originally defined in the scaling algorithm) to make things look good.


```
humanModel_TypeMeshes  
human
```

Image below shows the default and human meshes



Model Creation

Once the environment options have been properly loaded, the ModelCreator script is ready to construct the model(s). In the GUI this is accomplished by the "Create Model" button, and in the non-GUI version this step is automatically started upon executing the ModelCreator script. Note that these steps only creates the model structures in Matlab/Octave and does not export/write anything to file. The model is setup sequentially as follows:




1. Read human anthropometry
2. Read human model description
3. Read custom lengths (if any)
4. Set human scaling algorithm
5. Add custom markers (if any)
6. Create human model with arguments 1-5 (core/fnc_createHumanModel(args))

7. Read object descriptions (if any)
8. Set object setups
9. Add custom markers (if any)
10. Create object models with arguments 7-9 (`core/fnc_createObjectModel(args)`)
11. Compute object mass and inertia properties (if provided additionally)
12. Read custom constraints (if any)

Model Visualization

Pressing the Create Model button in the GUI plots the created model(s). Plotting options can be controlled via the check boxes on the right. In the non-GUI version simple plots can be created using the code below, and the plot details controlled using the booleans passed to the function `core/plottingUtils/fnc_plotting_plotModel.m`



```
% Function call format: 1) model, 2) plotJoints, 3) plotPoints, 4)
plotComs,
% 5) plotMarkers, 6) printLabels, 7) Mesh Alpha (transparency), 8)
markerSize,
% 9) rootDisplacement [x, y, z]
```

```
% Note that alpha transparency values are not yet allowed in octave
(so use 1.0)
fnc_plotting_plotModel (humanModel, 0, 0, 0, 0, 0, 1.0, 20, [0 0 0]);
for objID = 1:nObjects
    fnc_plotting_plotModel (objects(objID).objectModel, 0, 0, 0, 0, 0,
    1.0, 10, [objID*0.5 objID*0.5 0.0]);
end
```

Model Export

Writing of model lua file to disk can be controlled via the Save buttons on the right of the GUI. Note that the GUI preloads the filenames to be saved, but will not save automatically until told to do so (by pressing the button). In the non-GUI version file save is automatically executed at the end of model creation. If you do not wish to save files (e.g. to only visualize models), then just remove these fields or comment them in the environment file.



```
humanModel_Save %<----- Specify target for saving human lua
    model,
humanModel.lua  % remove this to not save the model (automatically)

objectModel1_Save %<----- Specify target for saving object 1 lua
    model
exoModel.lua

objectModel2_Save %<----- Specify target for saving object 2 lua
    model
boxModel.lua

combinedModel_Save %<----- Specify target for saving combined
    lua model
3DHumanExoBox.lua % The combined model consists of human + objects,
    and any custom constraints
```

Published with MATLAB® R2017a